



## **Introduction**

This document is to explain how to set up a Remote Desktop Connection in Windows XP. Remote Desktop Connections are used to remotely connect to another computer over a network, Internet or VPN.

## **Prerequisites**

Before we begin you will need;

- The IP Address Remote Computer (example 192.168.1.101)
- The Computer Name of the Remote Computer (example VDU101)
- Your Username for the Remote Computer (example JSmith)
- Your Username for the Remote Computer (example Password1)

**Date First Published** : 29/03/13

**Created By** : Paul Fox

**Version** : 1.1

**Lasted Updated** : 06/07/13

**Technical Level** : Low-Mid

## **Version History**

1.0 – First Published Version. (PF)


1.1 – Added Version History

## **Disclaimers & Acknowledgements**

*E&OE. Copying of this document, or text & images associated with it, is strictly prohibited. Imagery taken from Microsoft software is solely used for advice and training, Microsoft and Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. Pro Logic Computers (UK) Ltd or its agents accept no responsibility for the content of this document or results from actions taken by it. This document is provided as is, with no warranty or liability.*



## SETUP A REMOTE DESKTOP CONNECTION WINDOWS XP



Click on the **Start** normally in the bottom left corner.

Click **All programs**, **Accessories** and then **Remote Desktop Connection**.



**Remote Desktop Connection**

Computer: 192.168.1.101

User name: None specified

You will be asked for credentials when you connect.

Connect Cancel Help Options >>

Type in the IP Address we have given you this example shows **192.168.1.101** and click **Options >>**.

**Remote Desktop Connection**

General Display Local Resources Programs Experience Advanced

Logon settings

Enter the name of the remote computer.

Computer: 192.168.1.101

User name:

You will be asked for credentials when you connect.

Allow me to save credentials


Connection settings

Save the current connection settings to an RDP file or open a saved connection.


Save Save As... Open...

Connect Cancel Help Options <<

Click **Save As...**



Select **Desktop**, type in a **File Name**, in this example we have used **VDU101**, and click **Save**.



Now click **Cancel**.

You will now have an icon on your desktop to connect to that remote computer.

To connect, make sure you are connected to the network or VPN, simply Double Click the Remote Desktop Icon (VDU101) then you will be prompted for your username and password.